

```

1001 .CUSTOM GRAPHICS
1002 .VERSION 3.1
1003 .BY RICH TIETJENS
1010 GOTO 1030
1020 %(Y)=U;MU=U;Y=Y+W;RETURN
1030 CLEAR ;NT=1;X=0;INPUT "ASSY ADDR"Y,"BYTES WIDE"Q;R=Y;Z=1020;W=2
1035 INPUT "DOTS HIGH"H,"TABLE ADDR"T,"# CHARS"N
1037 PRINT #6,"TABLE REQUIRES",QbHbN," BYTESLAST ADDRESS:",T+QbHbN
1038 FOR S=0TO QbHbN;@(S)=0;MU=S;NEXT S;S=0
1039 FOR D=0TO 999;NEXT D
1040 CLEAR ;BOX Qb20-73,32-Hb5c2,Qb40+1,Hb5+1,3
1045 FOR U=1TO H;FOR C=1TO 8bQ;BOX Cb5-75,35-Ub5,4,4,3;NEXT C;NEXT U
1047 FOR I=1TO N
1050 C=-70;U=30
1060 BOX C,U,4,4,3;BOX C,U,4,4,3
1070 BOX C,U,4,4,TR(1)b((KN(1)<0)+1)
1080 C=C+JX(1)b5;U=U+JY(1)b5;IF C>Qb40-75IF TR(1)GOTO 1100
1090 GOTO 1060
1100 L=128;FOR U=1TO H;FOR C=1TO 8bQ
1110 @(S)=@(S)+PX(Cb5-75,35-Ub5)bL;L=Lc2;IF L=0L=128;S=S+1
1115 MU=@(S)
1120 NEXT C;NEXT U;NEXT I
1200 V=-43;GOSUB Z;V=6965;GOSUB Z
1210 V=10240;GOSUB Z;V=R+10;GOSUB Z
1220 V=-13871;GOSUB Z;W=1;V=112;GOSUB Z
1230 W=2;V=R+16;GOSUB Z;V=128;GOSUB Z
1240 W=1;V=48;GOSUB Z;V=128;GOSUB Z
1250 V=Qb8;GOSUB Z;V=H;GOSUB Z
1260 V=Q;GOSUB Z;V=H;GOSUB Z
1270 W=2;V=T;GOSUB Z;W=1;Y=T
1280 FOR S=0TO QbHbN;V=@(S);GOSUB Z;NEXT S
1300 CLEAR ;FOR I=0TO N-1;%(R+3)=10240+IbQb8+1;%(R+13)=128+I;CALLR
1310 NEXT I;CY=40
1320 PRINT "OK?";IF KP#13GOTO 1320
1330 INPUT "FILE #"F;PRINT 'START TAPE & PRESS "GO"
1340 IF KP#13GOTO 1340
1350 :PRINT ;NT=2;PRINT ;TV=Fc256;TV=RM;PRINT
1360 FOR X=RTO R+22STEP 2;PRINT #0,"%(",X,")=",%(X);NEXT X
1370 FOR X=TTO T+QbHbNSTEP 2;PRINT #0,"%(",X,")=",%(X);NEXT X
1380 PRINT ":RETURN ;RUN
1390 :RETURN ;.END

```

>  
BALLY BASIC

# CUSTOM GRAPHICS ASTRO BASIC

LOWERCASE = 1-BYTE KEYPAD WORDS. UNDERSCORES  
= SPACES. 1066 CHARACTERS

```
1001 .CUSTOM_GRAPHICS
1002 .VERSION_3.1
1003 .BY_RICH_TIETJENS
1010 goto 1030
1020 Z(Y)=V;MU=V;Y=Y+W;return
1030 clear ;NT=1;X=0;input "ASSY_ADDR"Y,"BYT
ES_WIDE"Q;R=Y;Z=1020;W=2
1035 input "DOTS_HIGH"H,"TABLE_ADDR"T,"#_CHA
RS"N
1037 print #6,"TABLE_REQUIRES",QxHxN,"_BYTES
LAST_ADDRESS:",T+QxHxN
1038 for S=0to QxHxN;@(S)=0;MU=S;next S;S=0
1039 for D=0to 999;next D
1040 clear ;box Qx20-73,32-Hx5+2,Qx40+1,Hx5+
1,3
1045 for U=1to H;for C=1to 8xQ;box Cx5-75,35
-Ux5,4,4,3;next C;next U
1047 for I=1to N
1050 C=-70;U=30
1060 box C,U,4,4,3;box C,U,4,4,3
1070 box C,U,4,4,TR(1)x((KN(1)<0)+1)
1080 C=C+JX(1)x5;U=U+JY(1)x5;if C>Qx40-75if
TR(1)goto 1100
1090 goto 1060
1100 L=128;for U=1to H;for C=1to 8xQ
1110 @(S)=@(S)+PX(Cx5-75,35-Ux5)xL;L=L+2;if
L=0L=128;S=S+1
1115 MU=@(S)
1120 next C;next U;next I
1200 V=-43;gosub Z;V=6965;gosub Z
1210 V=10240;gosub Z;V=R+10;gosub Z
1220 V=-13871;gosub Z;W=1;V=112;gosub Z
1230 W=2;V=R+16;gosub Z;V=128;gosub Z
1240 W=1;V=48;gosub Z;V=128;gosub Z
1250 V=Qx8;gosub Z;V=H;gosub Z
1260 V=Q;gosub Z;V=H;gosub Z
1270 W=2;V=T;gosub Z;W=1;Y=T
1280 for S=0to QxHxN;V=@(S);gosub Z;next S
1300 clear ;for I=0to N-1;Z(R+3)=10240+IxQx8
+1;Z(R+13)=128+I;CALLR
1310 next I;CY=40
1320 print "OK?";if KP#13goto 1320
1330 input "FILE_#"F;print 'START_TAPE_&_PRE
SS_"GO"
1340 if KP#13goto 1340
1350 ;print ;NT=2;print ;TV=F+256;TV=RM;prin
t
1360 for X=Rto R+22step 2;print #0,"%(",X,")
=",Z(X);next X
1370 for X=Tto T+QxHxNstep 2;print #0,"%(",X
,")=",Z(X);next X
1380 print ";return ;run
1390 ;return ;.END
```